



ROB - USER GUIDE


SETUP

Open OBS and select WebSocket Server Settings from the tool bar






Tick the enable
WebSocket
server option



Copy the connection
parameters

Enable the replay buffer from OBS's settings (not required)



Insert the connection parameters into the config.yaml file

```
! config.yaml
1 host: localhost
2 name: Rob
3 password: DV$a1877aMNq7gMw
4 port: 4455
```

COMMANDS

HELLO ROB START LISTENING

Starts the replay buffer

HELLO ROB STOP LISTENING

Stops the replay buffer

HELLO ROB SAVE THE REPLAY BUFFER

Saves the replay buffer

HELLO ROB START RECORDING

Starts the video recording, saving the replay buffer
in the process (when applicable)


HELLO ROB STOP RECORDING

Stops the video recording

THE UI

Recording status


Name selection



Settings button

Start the listener

One can also update the connection parameters via the user interface



ENJOY =)